

# **Caspase-6 Fluorometric Assay Kit (BN00040)**

(Catalog BN00040 -25, -100, -200, -400, Store kit at -20°C)

## I. Introduction:

Activation of ICE-family proteases/caspases initiates apoptosis in mammalian cells. The Caspase-6 Fluorometric Assay Kit provides a simple and convenient means for assaying the activity of caspases that recognize the sequence VEID. The assay is based on detection of cleavage of substrate VEID-AFC (AFC: 7-amino-4-trifluoromethyl coumarin). VEID-AFC emits blue light (λmax = 400 nm); upon cleavage of the substrate by Mch2 or related caspases, free AFC emits a yellow-green fluorescence (λmax = 505 nm), which can be quantified using a fluorometer or a fluorescence microtiter plate reader. Comparison of the fluorescence of AFC from an apoptotic sample with an uninduced control allows determination of the fold increase in caspase-6 activity.

#### II. Kit Contents:

Components	BN00040	BN00040	BN00040	BN00040
	25 assays	100 assays	200 assays	400 assays
Cell Lysis Buffer 2X Reaction Buffer	25 ml 2 ml	100 ml 4 x 2 ml	100 ml 16 ml	100 ml 32 ml
VEID-AFC (1 mM)	125 μl	0.5 ml	2 x 0.5 ml	2 x 1 ml
DTT (1 M)	100 μΙ	0.4 ml	0.4 ml	0.4 ml

### III. Caspase-6 Assay Protocol:

#### A. General Considerations

- Aliquot enough 2X Reaction Buffer for the number of assays to be performed. Add DTT to the 2X Reaction Buffer immediately before use (10 mM final concentration: add 10 μl of 1.0 M DTT stock per 1 ml of 2X Reaction Buffer).
- After thawing, store the Cell Lysis Buffer and 2X Reaction Buffer at 4°C.
- · Protect VEID-AFC from light.
- We recommend using a flat bottom, opaque, white or black 96-well plate for enhanced sensitivity.

## **B.** Assay Procedure

- Induce apoptosis in cells by desired method. Concurrently incubate a control culture without induction.
- Count cells and pellet 1-5 x 106 cells or use 50-250 μg cell lysates if protein concentration has been measured.
- 3. Resuspend cells in 50  $\mu$ l of chilled Cell Lysis Buffer. Incubate cells on ice for 10 minutes.
- 5. Add 50  $\mu$ l of 2X Reaction Buffer (containing 10 mM DTT) to each sample. Add 5  $\mu$ l of the 1 mM VEID-AFC substrate (50  $\mu$ M final concentration) and incubate at 37 °C for 1-2 hour.

 Read samples in a fluorometer equipped with a 400-nm excitation filter and 505-nm emission filter. For a plate-reading set-up, transfer the samples to a 96-well plate. You may also perform the entire assay directly in a 96-well plate.

Fold-increase in caspase-6 activity can be determined by comparing the results of treated samples with the level of the uninduced control.

## IV. Storage and Stability:

Store kit at -20°C (Store Cell Lysis Buffer and 2X Reaction Buffer at 4°C after opening). All reagents are stable for 6 months under proper storage conditions.

## FOR RESEARCH USE ONLY! Not to be used on humans.

Problems	Cause	So
Assay not working	Cells did not lyse completely	• R
	Experiment was not performed at optimal time after apoptosis induction	• P
	Plate read at incorrect wavelength	• 0
	Old DTT used	• A
High Background	Increased amount of cell lysate used	• R
	<ul> <li>Increased amounts of components added due to incorrect pipetting</li> </ul>	
	Incubation of cell samples for extended periods	• R
	Use of expired kit or improperly stored reagents	• A
	Contaminated cells	• 0
Lower signal levels	Cells did not initiate apoptosis	• 🗅
	Very few cells used for analysis	• R
	Use of samples stored for a long time	٠٠
	Incorrect setting of the equipment used to read samples	• R
	Allowing the reagents to sit for extended times on ice	• A
Samples with erratic readings	Uneven number of cells seeded in the wells	٠s
	Samples prepared in a different buffer	٠٠
	Adherent cells dislodged and lost at the time of experiment	• P
	Cell/ tissue samples were not completely homogenized	• U
	Samples used after multiple freeze-thaw cycles	• A



Troubleshoot as needed
Use fresh samples or store at correct temperatures until use
Check the equipment and the filter setting
• Troubleshoot if it interferes with the kit (run proper controls)
Thaw all components completely and mix gently before use
• Refer to datasheet & verify the correct incubation times and temperatures
Use calibrated pipettes and aliquot correctly
Pipette gently against the wall of the well/tubes
Use fresh components from the same kit
Fluorescence: Black plates; Absorbance: Clear plates